



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

***Rocky Enterprise Linux 9.2 Manual Pages on command 'Locale::RecodeData::NATS\_DANO.3pm'***

***\$ man Locale::RecodeData::NATS\_DANO.3pm***

Locale::RecodeData::NATS\_DANO(3User Contributed Perl DocumentatLocale::RecodeData::NATS\_DANO(3pm)

#### NAME

Locale::RecodeData::NATS\_DANO - Conversion routines for NATS\_DANO

#### SYNOPSIS

This module is internal to libintl. Do not use directly!

#### DESCRIPTION

This module is generated and contains the conversion tables and routines for NATS-DANO.

#### COMMENTS

The following comments have been extracted from the original charmap:

version: 1.0

source: ECMA registry

alias ISO-IR-9-1

Please note that aliases listed above are not necessarily valid!

#### CHARACTER TABLE

The following table is sorted in the same order as the original charmap. All character codes are in hexadecimal. Please read 'ISO-10646' as 'ISO-10646-UCS4'.

---

00		00000000		NULL (NUL)
01		00000001		START OF HEADING (SOH)
02		00000002		START OF TEXT (STX)
03		00000003		END OF TEXT (ETX)
04		00000004		END OF TRANSMISSION (EOT)
05		00000005		ENQUIRY (ENQ)
06		00000006		ACKNOWLEDGE (ACK)
07		00000007		BELL (BEL)
08		00000008		BACKSPACE (BS)
09		00000009		CHARACTER TABULATION (HT)
0A		0000000A		LINE FEED (LF)
0B		0000000B		LINE TABULATION (VT)
0C		0000000C		FORM FEED (FF)
0D		0000000D		CARRIAGE RETURN (CR)
0E		0000000E		SHIFT OUT (SO)
0F		0000000F		SHIFT IN (SI)
10		00000010		DATALINK ESCAPE (DLE)
11		00000011		DEVICE CONTROL ONE (DC1)
12		00000012		DEVICE CONTROL TWO (DC2)
13		00000013		DEVICE CONTROL THREE (DC3)
14		00000014		DEVICE CONTROL FOUR (DC4)
15		00000015		NEGATIVE ACKNOWLEDGE (NAK)
16		00000016		SYNCHRONOUS IDLE (SYN)
17		00000017		END OF TRANSMISSION BLOCK (ETB)
18		00000018		CANCEL (CAN)
19		00000019		END OF MEDIUM (EM)
1A		0000001A		SUBSTITUTE (SUB)
1B		0000001B		ESCAPE (ESC)
1C		0000001C		FILE SEPARATOR (IS4)
1D		0000001D		GROUP SEPARATOR (IS3)

1E | 0000001E | RECORD SEPARATOR (IS2)  
1F | 0000001F | UNIT SEPARATOR (IS1)  
20 | 00000020 | SPACE  
21 | 00000021 | EXCLAMATION MARK  
22 | 000000AB | LEFT-POINTING DOUBLE ANGLE QUOTATION MARK  
23 | 000000BB | RIGHT-POINTING DOUBLE ANGLE QUOTATION MARK  
24 | 00000024 | DOLLAR SIGN  
25 | 00000025 | PERCENT SIGN  
26 | 00000026 | AMPERSAND  
27 | 00000027 | APOSTROPHE  
28 | 00000028 | LEFT PARENTHESIS  
29 | 00000029 | RIGHT PARENTHESIS  
2A | 0000002A | ASTERISK  
2B | 0000002B | PLUS SIGN  
2C | 0000002C | COMMA  
2D | 0000002D | HYPHEN-MINUS  
2E | 0000002E | FULL STOP  
2F | 0000002F | SOLIDUS  
30 | 00000030 | DIGIT ZERO  
31 | 00000031 | DIGIT ONE  
32 | 00000032 | DIGIT TWO  
33 | 00000033 | DIGIT THREE  
34 | 00000034 | DIGIT FOUR  
35 | 00000035 | DIGIT FIVE  
36 | 00000036 | DIGIT SIX  
37 | 00000037 | DIGIT SEVEN  
38 | 00000038 | DIGIT EIGHT  
39 | 00000039 | DIGIT NINE  
3A | 0000003A | COLON  
3B | 0000003B | SEMICOLON  
3C | 0000003C | LESS-THAN SIGN  
3D | 0000003D | EQUALS SIGN  
3E | 0000003E | GREATER-THAN SIGN

3F | 0000003F | QUESTION MARK  
40 | 0000E018 | Unit space A E<lt>ISO-IR-8-1\_40E<gt>  
41 | 00000041 | LATIN CAPITAL LETTER A  
42 | 00000042 | LATIN CAPITAL LETTER B  
43 | 00000043 | LATIN CAPITAL LETTER C  
44 | 00000044 | LATIN CAPITAL LETTER D  
45 | 00000045 | LATIN CAPITAL LETTER E  
46 | 00000046 | LATIN CAPITAL LETTER F  
47 | 00000047 | LATIN CAPITAL LETTER G  
48 | 00000048 | LATIN CAPITAL LETTER H  
49 | 00000049 | LATIN CAPITAL LETTER I  
4A | 0000004A | LATIN CAPITAL LETTER J  
4B | 0000004B | LATIN CAPITAL LETTER K  
4C | 0000004C | LATIN CAPITAL LETTER L  
4D | 0000004D | LATIN CAPITAL LETTER M  
4E | 0000004E | LATIN CAPITAL LETTER N  
4F | 0000004F | LATIN CAPITAL LETTER O  
50 | 00000050 | LATIN CAPITAL LETTER P  
51 | 00000051 | LATIN CAPITAL LETTER Q  
52 | 00000052 | LATIN CAPITAL LETTER R  
53 | 00000053 | LATIN CAPITAL LETTER S  
54 | 00000054 | LATIN CAPITAL LETTER T  
55 | 00000055 | LATIN CAPITAL LETTER U  
56 | 00000056 | LATIN CAPITAL LETTER V  
57 | 00000057 | LATIN CAPITAL LETTER W  
58 | 00000058 | LATIN CAPITAL LETTER X  
59 | 00000059 | LATIN CAPITAL LETTER Y  
5A | 0000005A | LATIN CAPITAL LETTER Z  
5B | 000000C6 | LATIN CAPITAL LETTER AE  
5C | 000000D8 | LATIN CAPITAL LETTER O WITH STROKE  
5D | 000000C5 | LATIN CAPITAL LETTER A WITH RING ABOVE  
5E | 000025A0 | BLACK SQUARE  
5F | 0000005F | LOW LINE

60 | 0000E019 | Unit space B E<lt>ISO-IR-8-1\_60E<gt>  
61 | 00000061 | LATIN SMALL LETTER A  
62 | 00000062 | LATIN SMALL LETTER B  
63 | 00000063 | LATIN SMALL LETTER C  
64 | 00000064 | LATIN SMALL LETTER D  
65 | 00000065 | LATIN SMALL LETTER E  
66 | 00000066 | LATIN SMALL LETTER F  
67 | 00000067 | LATIN SMALL LETTER G  
68 | 00000068 | LATIN SMALL LETTER H  
69 | 00000069 | LATIN SMALL LETTER I  
6A | 0000006A | LATIN SMALL LETTER J  
6B | 0000006B | LATIN SMALL LETTER K  
6C | 0000006C | LATIN SMALL LETTER L  
6D | 0000006D | LATIN SMALL LETTER M  
6E | 0000006E | LATIN SMALL LETTER N  
6F | 0000006F | LATIN SMALL LETTER O  
70 | 00000070 | LATIN SMALL LETTER P  
71 | 00000071 | LATIN SMALL LETTER Q  
72 | 00000072 | LATIN SMALL LETTER R  
73 | 00000073 | LATIN SMALL LETTER S  
74 | 00000074 | LATIN SMALL LETTER T  
75 | 00000075 | LATIN SMALL LETTER U  
76 | 00000076 | LATIN SMALL LETTER V  
77 | 00000077 | LATIN SMALL LETTER W  
78 | 00000078 | LATIN SMALL LETTER X  
79 | 00000079 | LATIN SMALL LETTER Y  
7A | 0000007A | LATIN SMALL LETTER Z  
7B | 000000E6 | LATIN SMALL LETTER AE  
7C | 000000F8 | LATIN SMALL LETTER O WITH STROKE  
7D | 000000E5 | LATIN SMALL LETTER A WITH RING ABOVE  
7E | 00002013 | EN DASH  
7F | 0000007F | DELETE (DEL)

## AUTHOR

Copyright (C) 2002-2016 Guido Flohr <<http://www.guido-flohr.net/>>

(<<mailto:guido.flohr@cantanea.com>>), all rights reserved. See the source code for details!`code for details!`

## SEE ALSO

Locale::RecodeData(3), Locale::Recode(3), perl(1)

perl v5.34.0

2022-02-06

Locale::RecodeData::NATS\_DANO(3pm)