



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'endttyent.3'***

#### ***\$ man endttyent.3***

GETTTYENT(3)                      Linux Programmer's Manual                      GETTTYENT(3)

#### **NAME**

getttyent, getttynam, setttyent, endttyent - get ttys file entry

#### **SYNOPSIS**

```
#include <ttyent.h>

struct ttyent *getttyent(void);

struct ttyent *getttynam(const char *name);

int setttyent(void);

int endttyent(void);
```

#### **DESCRIPTION**

These functions provide an interface to the file `_PATH_TTYS` (e.g., `/etc/ttys`).

The function `setttyent()` opens the file or rewinds it if already open.

The function `endttyent()` closes the file.

The function `getttynam()` searches for a given terminal name in the file. It returns a pointer to a `ttyent` structure (description below).

The function `getttyent()` opens the file `_PATH_TTYS` (if necessary) and returns the first entry. If the file is already open, the next entry. The `ttyent` structure has the form:

```
struct ttyent {
    char *ty_name; /* terminal device name */
    char *ty_getty; /* command to execute, usually getty */
    char *ty_type; /* terminal type for termcap */
    int ty_status; /* status flags */
    char *ty_window; /* command to start up window manager */
}
```

```
char *ty_comment; /* comment field */
```

```
};
```

ty\_status can be:

```
#define TTY_ON    0x01 /* enable logins (start ty_getty program) */
```

```
#define TTY_SECURE 0x02 /* allow UID 0 to login */
```

## ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

??

?Interface	? Attribute	? Value	?
------------	-------------	---------	---

??

?gettyent(), setttyent(), ? Thread safety ? MT-Unsafe race:ttyent ?

?endttyent(), getttynam()	?	?	?
---------------------------	---	---	---

??

## CONFORMING TO

Not in POSIX.1. Present on the BSDs, and perhaps other systems.

## NOTES

Under Linux, the file /etc/ttys, and the functions described above, are not used.

## SEE ALSO

ttynam(3), ttyslot(3)

## COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.