



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'mousetweaks.1'***

**\$ man mousetweaks.1**

mousetweaks(1) General Commands Manual mousetweaks(1)

### **NAME**

mousetweaks - Accessibility enhancements for pointing devices

### **SYNOPSIS**

```
mousetweaks  [--dwell]  [--ssc]  [--dwell-time=FLOAT]  [--ssc-time=FLOAT]
[-m|--dwell-mode=STRING] [-c|--show-ctw] [-t|--threshold=INT] [-g|--geometry] [-s|--shut?
down] [-?|--help]
```

### **DESCRIPTION**

mousetweaks is a collection of accessibility enhancements for pointing devices. This man?

ual page describes the mousetweaks daemon.

### **OPTIONS**

--dwell

Automatically perform mouse clicks without using a physical button.

--ssc Trigger the secondary mouse button when the primary mouse button is held down for a specified amount of time.

--dwell-time=FLOAT

Time to keep the pointer motionless before a dwell click is performed. Range: 0.2 - 3.0 seconds.

--ssc-time=FLOAT

Time to hold the primary mouse button before a simulated secondary click is performed. Range: 0.5 - 3.0 seconds.

-m, --dwell-mode=STRING

Select a dwell mode. Available options: window - Select the click type from a win?

dow or a panel applet. gesture - Perform different clicks by moving in different directions.

**-c, --show-ctw**

Show the click-type window. Only useful in combination with --dwell-mode=window.

**-t, --threshold=INT**

Ignore small pointer movements. Range: 0 - 30 pixels.

**-g, --geometry**

Size and position of the click-type window. Expects a standard X Window System geometry string. ie. WIDTHxHEIGHT+X+Y

**-s, --shutdown**

Stop the mousetweaks daemon.

**--daemonize**

Start mousetweaks in the background, ie. spawn a child process.

**--login**

Start mousetweaks in login mode. Login mode enables workarounds specific to GDM.

Currently unused.

## FILES

**mousetweaks.pid**

The daemon creates a lock file in the \$XDG\_RUNTIME\_DIR directory to keep track of its state. On systems with no user runtime directory, the \$XDG\_CACHE\_HOME directory is used.

## BUGS

Report bugs to <<http://bugzilla.gnome.org/>> ?<http://bugzilla.gnome.org/>?

## AUTHORS

This manual page was written by Francesco Fumanti.

## LICENSE

Licenced under the GNU General Public License v3 or later.

**mousetweaks(1)**