



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'nroff.1'

\$ man nroff.1

NROFF(1) General Commands Manual NROFF(1)

NAME

nroff - use groff to format documents for TTY devices

SYNOPSIS

nroff [-CchipStUv] [-dcs] [-Mdir] [-mname] [-nnum] [-olist] [-rcn] [-Tname] [-Wwarning]
[-wwarning] [file ...]

nroff --help

nroff -v

nroff --version

DESCRIPTION

nroff formats documents written in the roff(7) language for typewriter-like devices such as terminal emulators.

GNU nroff emulates the traditional Unix nroff command using groff(1). nroff generates output via grotty(1), groff's TTY output device, which needs to know the character encoding scheme used by the terminal. Consequently, acceptable arguments to the -T option are ascii, latin1, utf8, and cp1047; any others are ignored. If neither the GROFF_TYPESETTER environment variable nor the -T command-line option (which overrides the environment variable) specifies a (valid) device, nroff consults the locale to select an appropriate output device. It first tries the locale(1) program, then checks several locale-related environment variables; see ?ENVIRONMENT?, below. If all of the foregoing fail, -Tascii is implied.

Whitespace is not permitted between an option and its argument. The -h and -c options are equivalent to grotty's options -h (using tabs in the output) and -c (using the old output

scheme instead of SGR escape sequences). The **-d**, **-C**, **-i**, **-M**, **-m**, **-n**, **-o**, **-r**, **-w**, and **-W** options have the effect described in *troff(1)*. In addition, *nroff* ignores **-e**, **-q**, and **-s** (which are not implemented in *troff*). The options **-p** (pic), **-t** (tbl), **-S** (safer), and **-U** (unsafe) are passed to *groff*. **-v** and **--version** show version information, while **--help** displays a usage message; all exit afterward.

ENVIRONMENT

GROFF_TYPESETTER

specifies the default output device for *groff*.

GROFF_BIN_PATH

is a colon-separated list of directories in which to search for the *groff* exe? cutable before searching in **PATH**. If unset, **/usr/bin** is used.

LC_ALL

LC_CTYPE

LANG

LESSCHARSET

are pattern-matched in this order for standard character encodings supported by *groff* in the event no **-T** option is given and **GROFF_TYPESETTER** is unset.

NOTES

Character definitions in the file **/usr/share/groff/1.22.4/tmac/tty-char.tmac** are loaded to replace unrepresentable glyphs.

SEE ALSO

groff(1), *troff(1)*, *grotty(1)*, *locale(1)*, *roff(7)*

groff 1.22.4

23 March 2022

NROFF(1)