



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'pthread_detach.3'

\$ man pthread_detach.3

PTHREAD_DETACH(3) Linux Programmer's Manual PTHREAD_DETACH(3)

NAME

pthread_detach - detach a thread

SYNOPSIS

```
#include <pthread.h>

int pthread_detach(pthread_t thread);

Compile and link with -pthread.
```

DESCRIPTION

The pthread_detach() function marks the thread identified by thread as detached. When a detached thread terminates, its resources are automatically released back to the system without the need for another thread to join with the terminated thread.

Attempting to detach an already detached thread results in unspecified behavior.

RETURN VALUE

On success, pthread_detach() returns 0; on error, it returns an error number.

ERRORS

EINVAL thread is not a joinable thread.

ESRCH No thread with the ID thread could be found.

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

??

?Interface ? Attribute ? Value ?

??

?pthread_detach() ? Thread safety ? MT-Safe ?

??

CONFORMING TO

POSIX.1-2001, POSIX.1-2008.

NOTES

Once a thread has been detached, it can't be joined with `pthread_join(3)` or be made joinable again.

A new thread can be created in a detached state using `pthread_attr_setdetachstate(3)` to set the detached attribute of the `attr` argument of `pthread_create(3)`.

The detached attribute merely determines the behavior of the system when the thread terminates; it does not prevent the thread from being terminated if the process terminates using `exit(3)` (or equivalently, if the main thread returns).

Either `pthread_join(3)` or `pthread_detach()` should be called for each thread that an application creates, so that system resources for the thread can be released. (But note that the resources of any threads for which one of these actions has not been done will be freed when the process terminates.)

EXAMPLES

The following statement detaches the calling thread:

```
pthread_detach(pthread_self());
```

SEE ALSO

`pthread_attr_setdetachstate(3)`, `pthread_cancel(3)`, `pthread_create(3)`, `pthread_exit(3)`, `pthread_join(3)`, `pthreads(7)`

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.