



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'truncate.1'

\$ man truncate.1

TRUNCATE(1)

User Commands

TRUNCATE(1)

NAME

truncate - shrink or extend the size of a file to the specified size

SYNOPSIS

truncate OPTION... FILE...

DESCRIPTION

Shrink or extend the size of each FILE to the specified size

A FILE argument that does not exist is created.

If a FILE is larger than the specified size, the extra data is lost. If a FILE is

shorter, it is extended and the sparse extended part (hole) reads as zero bytes.

Mandatory arguments to long options are mandatory for short options too.

-c, --no-create

do not create any files

-o, --io-blocks

treat SIZE as number of IO blocks instead of bytes

-r, --reference=RFILE

base size on RFILE

-s, --size=SIZE

set or adjust the file size by SIZE bytes

--help display this help and exit

--version

output version information and exit

K,M,G,T,P,E,Z,Y (powers of 1024) or KB,MB,... (powers of 1000). Binary prefixes can be used, too: KiB=K, MiB=M, and so on.

SIZE may also be prefixed by one of the following modifying characters: '+' extend by, '-' reduce by, '<' at most, '>' at least, '/' round down to multiple of, '%' round up to multiple of.

AUTHOR

Written by Padraig Brady.

REPORTING BUGS

GNU coreutils online help: <<https://www.gnu.org/software/coreutils/>>

Report any translation bugs to <<https://translationproject.org/team/>>

COPYRIGHT

Copyright ? 2020 Free Software Foundation, Inc. License GPLv3+: GNU GPL version 3 or later <<https://gnu.org/licenses/gpl.html>>.

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

SEE ALSO

dd(1), truncate(2), ftruncate(2)

Full documentation <<https://www.gnu.org/software/coreutils/truncate>>

or available locally via: info '(coreutils) truncate invocation'