



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'watchgnupg.1'

\$ man watchgnupg.1

WATCHGNUPG(1)

GNU Privacy Guard 2.2

WATCHGNUPG(1)

NAME

watchgnupg - Read and print logs from a socket

SYNOPSIS

watchgnupg [--force] [--verbose] socketname

DESCRIPTION

Most of the main utilities are able to write their log files to a Unix Domain socket if configured that way. watchgnupg is a simple listener for such a socket. It ameliorates the output with a time stamp and makes sure that long lines are not interspersed with log output from other utilities. This tool is not available for Windows.

watchgnupg is commonly invoked as

watchgnupg --force \$(gpgconf --list-dirs socketdir)/S.log

OPTIONS

watchgnupg understands these options:

--force

Delete an already existing socket file.

--tcp n

Instead of reading from a local socket, listen for connects on TCP port n.

--time-only

Do not print the date part of the timestamp.

--verbose

Enable extra informational output.

--version

Print version of the program and exit.

--help Display a brief help page and exit.

EXAMPLES

```
$ watchgnupg --force --time-only $(gpgconf --list-dirs socketdir)/S.log
```

This waits for connections on the local socket (e.g. ?/home/foo/.gnupg/S.log?) and shows all log entries. To make this work the option log-file needs to be used with all modules which logs are to be shown. The suggested entry for the configuration files is:

```
log-file socket://
```

If the default socket as given above and returned by "echo \$(gpgconf --list-dirs socket? dir)/S.log" is not desired an arbitrary socket name can be specified, for example ?socket://home/foo/bar/mysocket?. For debugging purposes it is also possible to do remote logging. Take care if you use this feature because the information is send in the clear over the network. Use this syntax in the conf files:

```
log-file tcp://192.168.1.1:4711
```

You may use any port and not just 4711 as shown above; only IP addresses are supported (v4 and v6) and no host names. You need to start watchgnupg with the tcp option. Note that under Windows the registry entry HKCU\Software\GNU\GnuPG:DefaultLogFile can be used to change the default log output from stderr to whatever is given by that entry. However the only useful entry is a TCP name for remote debugging.

SEE ALSO

gpg(1), gpgsm(1), gpg-agent(1), scdaemon(1)

The full documentation for this tool is maintained as a Texinfo manual. If GnuPG and the info program are properly installed at your site, the command

```
info gnupg
```

should give you access to the complete manual including a menu structure and an index.