Rocky Enterprise Linux 9.2 Manual Pages on command 'xconsole.1'

$ man xconsole.1

XCONSOLE(1)   General Commands Manual   XCONSOLE(1)

NAME

   xconsole - monitor system console messages with X

SYNOPSIS

   xconsole [-toolkitoption ...] [-file file-name] [-notify] [-stripNonprint] [-daemon]

   [-verbose] [-exitOnFail]

DESCRIPTION

   The xconsole program displays messages which are usually sent to /dev/console.

OPTIONS

   Xconsole accepts all of the standard X Toolkit command line options along with the addi?

   tional options listed below:

   -file file-name

        To monitor some other device, use this option to specify the device name. This

        does not work on regular files as they are always ready to be read from.

   -notify -nonotify

        When new data are received from the console and the notify option is set, the icon

        name of the application has " *" appended, so that it is evident even when the ap?

        plication is iconified. -notify is the default.

   -daemon This option causes xconsole to place itself in the background, using fork/exit.

   -verbose

        When set, this option directs xconsole to display an informative message in the

        first line of the text buffer.

   -exitOnFail

When set, this option directs xconsole to exit when it is unable to redirect the console output.

-saveLines count

When set, xconsole only preserves count lines of message history instead of grow?
ing the text buffer without bound (a count of zero - the default - is treated as
placing no limit on the history).

X DEFAULTS

This program uses the Athena Text widget, look in the Athena Widget Set documentation for controlling it.

Xconsole otherwise accepts resources of the same names as the command-line options (with?
out the leading dash). "file" is a string type, "saveLines" an integer, and the remaining
options are booleans.

WIDGETS

In order to specify resources, it is useful to know the hierarchy of the widgets which
compose xconsole. In the notation below, indentation indicates hierarchical structure.
The widget class name is given first, followed by the widget instance name.

XConsole xconsole

XConsole text

ENVIRONMENT

DISPLAY to get the default host and display number.

XENVIRONMENT

to get the name of a resource file that overrides the global resources stored in
the RESOURCE_MANAGER property.

FILES

/etc/X11/app-defaults/XConsole

specifies required resources

SEE ALSO

X(7), xrdb(1), Athena Text widget

AUTHOR

Keith Packard (MIT X Consortium)

X Version 11   xconsole 1.0.7   XCONSOLE(1)