



Rocky Enterprise Linux 9.2 Manual Pages on command 'nl.1'

C:\>man nl.1

NL(1) User Commands NL(1)

NAME

nl - number lines of files

SYNOPSIS

nl [OPTION]... [FILE]...

DESCRIPTION

Write each FILE to standard output, with line numbers added.

With no FILE, or when FILE is -, read standard input.

Mandatory arguments to long options are mandatory for short options too.

-b, --body-numbering=STYLE

use STYLE for numbering body lines

-d, --section-delimiter=CC

use CC for logical page delimiters

-f, --footer-numbering=STYLE

use STYLE for numbering footer lines

-h, --header-numbering=STYLE

use STYLE for numbering header lines

-i, --line-increment=NUMBER

line number increment at each line

-l, --join-blank-lines=NUMBER

group of NUMBER empty lines counted as one

-n, --number-format=FORMAT

insert line numbers according to FORMAT

-p, --no-renumber

do not reset line numbers for each section

-s, --number-separator=STRING

add STRING after (possible) line number

-v, --starting-line-number=NUMBER

first line number for each section

-w, --number-width=NUMBER

use NUMBER columns for line numbers

--help display this help and exit

--version

output version information and exit

Default options are: -bt -d\'\' -fn -hn -i1 -l1 -n\'rn\' -s<TAB> -v1 -w6

CC are two delimiter characters used to construct logical page delimiters; a miss?

ing second character implies '\':.

STYLE is one of:

a number all lines

t number only nonempty lines

n number no lines

pBRE number only lines that contain a match for the basic regular expression, BRE

FORMAT is one of:

ln left justified, no leading zeros

rn right justified, no leading zeros

rz right justified, leading zeros

AUTHOR

Written by Scott Bartram and David MacKenzie.

REPORTING BUGS

GNU coreutils online help: <<https://www.gnu.org/software/coreutils/>>

Report nl translation bugs to <<https://translationproject.org/team/>>

COPYRIGHT

Copyright ? 2018 Free Software Foundation, Inc. License GPLv3+: GNU GPL version 3

or later <<https://gnu.org/licenses/gpl.html>>.

This is free software: you are free to change and redistribute it. There is NO

WARRANTY, to the extent permitted by law.

SEE ALSO

Full documentation at: <<https://www.gnu.org/software/coreutils/nl>>

or available locally via: info '(coreutils) nl invocation'

GNU coreutils 8.30

September 2019

NL(1)