



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'pod2html.1'***

**C:\>man pod2html.1**

POD2HTML(1)

Perl Programmers Reference Guide

POD2HTML(1)

### NAME

pod2html - convert .pod files to .html files

### SYNOPSIS

```
pod2html --help --htmldir=<name> --htmlroot=<URL>
        --infile=<name> --outfile=<name>
        --podpath=<name>:...:<name> --podroot=<name>
        --cachedir=<name> --flush --recurse --norecurse
        --quiet --noquiet --verbose --noverbose
        --index --noindex --backlink --nobacklink
        --header --noheader --poderrors --nopoderrors
        --css=<URL> --title=<name>
```

### DESCRIPTION

Converts files from pod format (see perlpod) to HTML format.

### ARGUMENTS

pod2html takes the following arguments:

help

--help

Displays the usage message.

#### htmldir

--htmldir=name

Sets the directory to which all cross references in the resulting HTML file will be relative. Not passing this causes all links to be absolute since this is the value that tells Pod::Html the root of the documentation tree.

Do not use this and --htmlroot in the same call to pod2html; they are mutually exclusive.

#### htmlroot

--htmlroot=URL

Sets the base URL for the HTML files. When cross-references are made, the HTML root is prepended to the URL.

Do not use this if relative links are desired: use --htmldir instead.

Do not pass both this and --htmldir to pod2html; they are mutually exclusive.

#### infile

--infile=name

Specify the pod file to convert. Input is taken from STDIN if no infile is specified.

#### outfile

--outfile=name

Specify the HTML file to create. Output goes to STDOUT if no outfile is specified.

podroot

--podroot=name

Specify the base directory for finding library pods.

podpath

--podpath=name:....:name

Specify which subdirectories of the podroot contain pod files whose HTML converted forms can be linked-to in cross-references.

cachedir

--cachedir=name

Specify which directory is used for storing cache. Default directory is the current working directory.

flush

--flush

Flush the cache.

backlink

--backlink

Turn =head1 directives into links pointing to the top of the HTML file.

nobacklink

--nobacklink

Do not turn =head1 directives into links pointing to the top of the HTML file (default behaviour).

header

--header

Create header and footer blocks containing the text of the "NAME" section.

noheader

--noheader

Do not create header and footer blocks containing the text of the "NAME" section (default behaviour).

poderrors

--poderrors

Include a "POD ERRORS" section in the outfile if there were any POD errors in the infile (default behaviour).

nopoderrors

--nopoderrors

Do not include a "POD ERRORS" section in the outfile if there were any POD errors in the infile.

index

--index

Generate an index at the top of the HTML file (default behaviour).

noindex

--noindex

Do not generate an index at the top of the HTML file.

recurse

--recurse

Recurse into subdirectories specified in podpath (default behaviour).

norecurse

--norecurse

Do not recurse into subdirectories specified in podpath.

css

--css=URL

Specify the URL of cascading style sheet to link from resulting HTML file.

Default is none style sheet.

title

--title=title

Specify the title of the resulting HTML file.

quiet

--quiet

Don't display mostly harmless warning messages.

noquiet

--noquiet

Display mostly harmless warning messages (default behaviour). But this is not

the same as "verbose" mode.

verbose

--verbose

Display progress messages.

noverbose

--noverbose

Do not display progress messages (default behaviour).

#### AUTHOR

Tom Christiansen, <tchrist@perl.com>.

#### BUGS

See Pod::Html for a list of known bugs in the translator.

#### SEE ALSO

perlpod, Pod::Html

#### COPYRIGHT

This program is distributed under the Artistic License.

perl v5.30.0

2022-10-05

POD2HTML(1)