



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'sane-tamarack.5'***

**C:\>man sane-tamarack.5**

sane-tamarack(5)          SANE Scanner Access Now Easy          sane-tamarack(5)

### NAME

sane-tamarack - SANE backend for Tamarack flatbed scanners

### DESCRIPTION

The sane-tamarack library implements a SANE (Scanner Access Now Easy) backend that provides access to the following Tamarack flatbed scanners:

Artiscan 6000C

Artiscan 8000C

Artiscan 12000C

### DEVICE NAMES

This backend expects device names of the form:

special

Where special is the path-name for the special device that corresponds to a SCSI scanner. The special device name must be a generic SCSI device or a symlink to such a device. The program sane-find-scanner helps to find out the correct device. Under Linux, such a device name could be /dev/sga or /dev/sge, for example. See

sane-scsi(5) for details.

## FILES

@CONFIGDIR@/tamarack.conf

The backend configuration file (see also description of SANE\_CONFIG\_DIR below).

@LIBDIR@/libsane-tamarack.a

The static library implementing this backend.

@LIBDIR@/libsane-tamarack.so

The shared library implementing this backend (present on systems that support dynamic loading).

## ENVIRONMENT

SANE\_CONFIG\_DIR

This environment variable specifies the list of directories that may contain the configuration file. Under UNIX, the directories are separated by a colon (:), under OS/2, they are separated by a semi-colon (;). If this variable is not set, the configuration file is searched in two default directories: first, the current working directory (".") and then in @CONFIGDIR@. If the value of the environment variable ends with the directory separator character, then the default directories are searched after the explicitly specified directories. For example, setting SANE\_CONFIG\_DIR to "/tmp/config:" would result in directories "tmp/config", ".", and @CONFIGDIR@" being searched (in this order).

SANE\_DEBUG\_TAMARACK

If the library was compiled with debug support enabled, this environment variable controls the debug level for this backend. Higher debug levels increase the verbosity of the output.

Example: export SANE\_DEBUG\_TAMARACK=4

SEE ALSO

sane(7), sane-scsi(5)

AUTHOR

Roger Wolff

@PACKAGEVERSION@

14 Jul 2008

sane-tamarack(5)