



Windows PowerShell Get-Help on Cmdlet 'Add-AzDataLakeStoreTrustedIdProvider'

PS:\>Get-HELP Add-AzDataLakeStoreTrustedIdProvider -Full

NAME

Add-AzDataLakeStoreTrustedIdProvider

SYNOPSIS

Adds a trusted identity provider to the specified Data Lake Store account.

SYNTAX

```
Add-AzDataLakeStoreTrustedIdProvider [-Account] <System.String> [-Name] <System.String> [-ProviderEndpoint]
<System.String> [[-ResourceGroupName] <System.String>]
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Add-AzDataLakeStoreTrustedIdProvider cmdlet adds a trusted identity provider to the specified Data Lake Store account.

-Account <System.String>

The name of the Data Lake Store account to add the specified trusted identity provider to.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the trusted identity provider to add

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ProviderEndpoint <System.String>

The valid trusted provider endpoint in the format: https://sts.windows.net/<provider identity>"

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group under which the account to add the trusted identity provider is.

Required? false

Position? 3

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.DataLakeStore.Models.DataLakeStoreTrustedIdProvider

NOTES

----- Example 1: Add a trusted identity provider -----

```
Add-AzDataLakeStoreTrustedIdProvider -AccountName "ContosoADL" -Name MyProvider -ProviderEndpoint  
"https://sts.windows.net/6b04908c-b91f-40ce-8024-7ee8a4fd6150"
```

Adds the provider "MyProvider" to account "ContosoADL" with the provider endpoint
"https://sts.windows.net/6b04908c-b91f-40ce-8024-7ee8a4fd6150"

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datalakestore/add-azdatalakestoretrustedidprovider>