



Windows PowerShell Get-Help on Cmdlet 'Add-AzTrafficManagerCustomHeaderToProfile'

PS:\>Get-HELP Add-AzTrafficManagerCustomHeaderToProfile -Full

NAME

Add-AzTrafficManagerCustomHeaderToProfile

SYNOPSIS

Adds custom header information to a local Traffic Manager profile object.

SYNTAX

```
                                Add-AzTrafficManagerCustomHeaderToProfile                                [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
                                <System.String> -TrafficManagerProfile <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile>
-Value <System.String> [-Confirm] [-WhatIf]
                                [<CommonParameters>]
```

DESCRIPTION

The Add-AzTrafficManagerCustomHeaderToProfile cmdlet adds custom header information to a local Azure Traffic Manager profile object. You can get a profile by using the New-AzTrafficManagerProfile or Get-AzTrafficManagerProfile cmdlets.

This cmdlet operates on the local profile object. Commit your changes to the profile for Traffic Manager by using the Set-AzTrafficManagerProfile cmdlet.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the custom header information to be added.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-TrafficManagerProfile <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile>

Specifies a local TrafficManagerProfile object. This cmdlet modifies this local object. To obtain a TrafficManagerProfile object, use the

Get-AzTrafficManagerProfile cmdlet.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Value <System.String>

Specifies the value of the custom header information to be added.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile

OUTPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile

NOTES

---- Example 1: Add custom header information to a profile ----

```
$TrafficManagerProfile = Get-AzTrafficManagerProfile -Name "ContosoProfile" -ResourceGroupName  
"ResourceGroup11"  
Add-AzTrafficManagerCustomHeaderToProfile -TrafficManagerProfile $TrafficManagerProfile -Name "host" -Value  
"www.contoso.com"  
Set-AzTrafficManagerProfile -TrafficManagerProfile $TrafficManagerProfile
```

The first command gets an Azure Traffic Manager profile by using the Get-AzTrafficManagerProfile cmdlet. The command stores the local profile in the

\$TrafficManagerProfile variable. The second command adds custom header information to the profile stored in \$TrafficManagerProfile. The final command updates the profile in Traffic Manager to match the local value in \$TrafficManagerProfile.

<https://learn.microsoft.com/powershell/module/az.trafficmanager/add-aztrafficmanagercustomheadertoprofile>

Remove-AzTrafficManagerCustomHeaderFromProfile

Get-AzTrafficManagerProfile

Set-AzTrafficManagerProfile