



Windows PowerShell Get-Help on Cmdlet 'Add-AzVmssAdditionalUnattendContent'

PS:\>Get-HELP Add-AzVmssAdditionalUnattendContent -Full

NAME

Add-AzVmssAdditionalUnattendContent

SYNOPSIS

Adds information to the unattended Windows Setup answer file.

SYNTAX

Add-AzVmssAdditionalUnattendContent [-VirtualMachineScaleSet]

<Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet> [[-PassName] {OobeSystem}]

[[-ComponentName] {MicrosoftWindowsShellSetup}] [[-SettingName] {AutoLogon | FirstLogonCommands}] [[-Content]

<System.String>] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]

[<CommonParameters>]

DESCRIPTION

The Add-AzVmssAdditionalUnattendContent cmdlet adds information to the unattended Windows Setup answer file.

PARAMETERS

-ComponentName <System.Nullable`1[Microsoft.Azure.Management.Compute.Models.ComponentNames]>

Specifies the name of the component to configure with the added content. The only allowable value is Microsoft-Windows-Shell-Setup.

Required?	false
Position?	2
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-Content <System.String>

Specifies the XML formatted content that is added to the unattend.xml file for the specified path and component.

Required?	false
Position?	4
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-PassName <System.Nullable`1[Microsoft.Azure.Management.Compute.Models.PassNames]>

Specifies the name of the pass that the content applies to. The only allowable value is oobeSystem.

Required?	false
-----------	-------

Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-SettingName <System.Nullable`1[Microsoft.Azure.Management.Compute.Models.SettingNames]>

Specifies the name of the setting to which the content applies. The acceptable values for this parameter are:: -

FirstLogonCommands

- AutoLogon

Required? false
Position? 3
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-VirtualMachineScaleSet <Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet>

Specify the virtual machine Scale Set object. You can use the New-AzVmssConfig (./New-AzVmssConfig.md)cmdlet to create the object.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName, ByValue)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False

Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet

System.Nullable`1[[Microsoft.Azure.Management.Compute.Models.PassNames, Microsoft.Azure.Management.Compute, Version=23.0.0.0, Culture=neutral, PublicKeyToken=31bf3856ad364e35]]

System.Nullable`1[[Microsoft.Azure.Management.Compute.Models.ComponentNames, Microsoft.Azure.Management.Compute, Version=23.0.0.0, Culture=neutral, PublicKeyToken=31bf3856ad364e35]]

Microsoft.Azure.Management.Compute, Version=23.0.0.0, Culture=neutral,
PublicKeyToken=31bf3856ad364e35]]

System.String

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet

NOTES

Example 1: Add information to the unattended Windows Setup answer file

```
Add-AzVmssAdditionalUnattendContent -VirtualMachineScaleSet $VMSS -ComponentName $AUCComponentName  
-Content $AUCContent -PassName $AUCPassName -SettingName  
$AUCSetting
```

This command adds information to the unattended Windows Setup answer file.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/add-azvmssadditionalunattendcontent>

New-AzVmssConfig

