



Windows PowerShell Get-Help on Cmdlet 'Disable-AzBatchJobSchedule'

PS:\>Get-HELP Disable-AzBatchJobSchedule -Full

NAME

Disable-AzBatchJobSchedule

SYNOPSIS

Disables a Batch job schedule.

SYNTAX

```
Disable-AzBatchJobSchedule [-Id] <System.String> -BatchContext
<Microsoft.Azure.Commands.Batch.BatchAccountContext> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

DESCRIPTION

The Disable-AzBatchJobSchedule cmdlet disables an Azure Batch job schedule. If you disable a schedule, jobs are not created according to that schedule. You can enable a disabled schedule later.

PARAMETERS

-BatchContext <Microsoft.Azure.Commands.Batch.BatchAccountContext>

Specifies the BatchAccountContext instance that this cmdlet uses to interact with the Batch service. If you use the Get-AzBatchAccount cmdlet to get your

BatchAccountContext, then Microsoft Entra authentication will be used when interacting with the Batch service. To use shared key authentication instead, use the

Get-AzBatchAccountKey cmdlet to get a BatchAccountContext object with its access keys populated. When using shared key authentication, the primary access key is

used by default. To change the key to use, set the BatchAccountContext.KeyInUse property.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Id <System.String>

Specifies the ID of the job schedule that this cmdlet disables.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Batch.BatchAccountContext

OUTPUTS

System.Void

NOTES

----- Example 1: Disable a job schedule -----

Disable-AzBatchJobSchedule -Id "JobSchedule17" -BatchContext \$Context

This command disables the job schedule that has the ID JobSchedule17. Use the Get-AzBatchAccountKey cmdlet to assign a context to the \$Context variable.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.batch/disable-azbatchjobschedule>

Enable-AzBatchJobSchedule

Get-AzBatchAccountKey

Get-AzBatchJobSchedule

New-AzBatchJobSchedule

Remove-AzBatchJobSchedule

Stop-AzBatchJobSchedule

Azure Batch Cmdlets