



Windows PowerShell Get-Help on Cmdlet 'Disable-AzDataCollection'

PS:\>Get-HELP Disable-AzDataCollection -Full

NAME

Disable-AzDataCollection

SYNOPSIS

Opts out of collecting data to improve the Azure PowerShell cmdlets. Data is collected by default unless you explicitly opt out.

SYNTAX

```
Disable-AzDataCollection [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The `Disable-AzDataCollection` cmdlet is used to opt out of data collection. Azure PowerShell automatically collects telemetry data by default. To disable data

collection, you must explicitly opt-out. Microsoft aggregates collected data to identify patterns of usage, to identify common issues, and to improve the experience

of Azure PowerShell. Microsoft Azure PowerShell doesn't collect any private or personal data. If you've previously opted

out, run the `Enable-AzDataCollection` cmdlet

to re-enable data collection for the current user on the current machine.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

None

OUTPUTS

System.Void

NOTES

-- Example 1: Disabling data collection for the current user --

Disable-AzDataCollection

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/disable-azdatacollection>

Enable-AzDataCollection

