



Windows PowerShell Get-Help on Cmdlet 'Disable-AzHDInsightAzureMonitor'

PS:\>Get-HELP Disable-AzHDInsightAzureMonitor -Full

NAME

Disable-AzHDInsightAzureMonitor

SYNOPSIS

Disables Azure Monitor in a specified HDInsight cluster.

SYNTAX

```
Disable-AzHDInsightAzureMonitor [[-ResourceGroupName] <System.String>] [-ClusterName] <System.String>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Disable-AzHDInsightAzureMonitor [-InputObject] <Microsoft.Azure.Commands.HDInsight.Models.AzureHDInsightCluster>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Disable-AzHDInsightAzureMonitor [-ResourceId] <System.String> [-DefaultProfile
```

```
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
```

[<CommonParameters>]

DESCRIPTION

This cmdlet Disable-AzHDInsightAzureMonitor disables Azure Monitor in a specified HDInsight cluster.

PARAMETERS

-ClusterName <System.String>

Gets or sets the name of the cluster.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.HDInsight.Models.AzureHDInsightCluster>

Gets or sets the input object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Gets or sets the name of the resource group.

Required? false

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Gets or sets the resource id.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.HDInsight.Models.AzureHDInsightCluster

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

Cluster info

\$clusterName = "your-hadoop-001"

```
$resourceGroupName = "Group"
```

```
Disable-AzHDInsightAzureMonitor -ClusterName $clusterName -ResourceGroupName $resourceGroupName
```

This cmdlet disables the azure monitor in a specified HDInsight cluster.

----- Example 2 -----

```
# Cluster info
```

```
$clusterName = "your-hadoop-001"
```

```
$cluster=Get-AzHDInsightCluster -ClusterName $clusterName
```

```
$cluster | Disable-AzHDInsightAzureMonitor
```

This cmdlet disables the azure monitor in a specified HDInsight cluster with pipeline.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.hdinsight/disable-azhdinsightazuremonitor>

Enable-AzHDInsightAzureMonitor

Get-AzHDInsightAzureMonitor