



Windows PowerShell Get-Help on Cmdlet 'Disable-AzHDInsightMonitoring'

PS:\>Get-HELP Disable-AzHDInsightMonitoring -Full

NAME

Disable-AzHDInsightMonitoring

SYNOPSIS

Disables the Classic Azure Monitor logs integration on an HDInsight cluster and relevant logs will stop flowing to the monitoring workspace specified during enable.

SYNTAX

```
Disable-AzHDInsightMonitoring [-Name] <System.String> [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>  
[-ResourceGroupName <System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Disable-AzHDInsightMonitoring cmdlet disables the Classic Azure Monitor logs integration on an HDInsight cluster.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

The name of the cluster to disable Monitoring.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group of the cluster.

Required? false
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Boolean

NOTES

Disable-AzHDInsightMonitoring -Name testcluster

True

Monitoring will be disabled on the HDInsight cluster and relevant logs will stop flowing to the monitoring workspace.

----- Example 2 -----

Disable-AzHDInsightMonitoring -Name testcluster -ResourceGroupName testrg

True

Monitoring will be disabled on the HDInsight cluster and relevant logs will stop flowing to the monitoring workspace.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.hdinsight/disable-azhdinsightmonitoring>