



Windows PowerShell Get-Help on Cmdlet 'Disable-AzRecoveryServicesBackupAutoProtection'

PS:\>Get-HELP Disable-AzRecoveryServicesBackupAutoProtection -Full

NAME

Disable-AzRecoveryServicesBackupAutoProtection

SYNOPSIS

Disables auto backup for a protectable item.

SYNTAX

```
Disable-AzRecoveryServicesBackupAutoProtection [-InputItem]

<Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.ProtectableItemBase>

[-BackupManagementType] {AzureWorkload} [-WorkloadType] {MSSQL} [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-PassThru] [-VaultId]
<System.String> [-Confirm] [-WhatIf]

[<CommonParameters>]
```

DESCRIPTION

The Disable-AzRecoveryServicesBackupAutoProtection cmdlet disables protection on a protectable item.

PARAMETERS

-BackupManagementType

<Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.BackupManagementType>

The class of resources being protected. Currently the value supported for this cmdlet is AzureWorkload

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputItem <Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.ProtectableItemBase>

Item Id

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Return the result for auto protection.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-VaultId <System.String>

ARM ID of the Recovery Services Vault.

Required? false
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-WorkloadType <Microsoft.Azure.Commands.RecoveryServices.Backup.Cmdlets.Models.WorkloadType>

Workload type of the resource. The current supported value is "MSSQL"

Required? true
Position? 2
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

```
$vault = Get-AzRecoveryServicesVault -ResourceGroupName "resourceGroup" -Name "vaultName"
```

```
$container = Get-AzRecoveryServicesBackupContainer -ContainerType AzureVMAppContainer -Status "Registered"
```

```
-FriendlyName "TestSQLServerVM" -VaultId $vault.ID
```

```
Get-AzRecoveryServicesBackupProtectableItem -Container $container -WorkloadType "MSSQL" -ItemType  
"SQLInstance" -Name "MSSQLInstance" |
```

```
Disable-AzRecoveryServicesBackupAutoProtection -BackupManagementType "AzureWorkload" -WorkloadType  
"MSSQL"
```

The first cmdlet gets the Backup container of type AzureVMAppContainer. The second cmdlet gets the protectable BackupItem and disables auto protection.

----- Example 2 -----

```
Disable-AzRecoveryServicesBackupAutoProtection -BackupManagementType AzureVM -InputItem  
<ProtectableItemBase> -VaultId $vault.ID -WorkloadType AzureVM
```

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/disable-azrecoveryservicesbackupautoprotection>