

Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Disable-AzStackHClAttestation'

| 'S:\>Get-HELF | P Disable-A | \zStackHCl <i>i</i> | Attestation -Full |
|---------------------------|-------------|---------------------|-------------------|
|---------------------------|-------------|---------------------|-------------------|

NAME

Disable-AzStackHCIAttestation

SYNOPSIS

Disable-AzStackHCIAttestation disables IMDS Attestation on the host

SYNTAX

Disable-AzStackHCIAttestation [[-ComputerName] <String>] [-Credential <PSCredential>] [-RemoveVM] [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

DESCRIPTION

Disable-AzStackHCIAttestation disables IMDS Attestation on the host

PARAMETERS

-ComputerName <String>

Specifies the AzureStack HCI host to perform the operation on.

Required? false

Position? 1

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Credential <PSCredential>

Specifies the credential for the ComputerName.

Default is the current user executing the Cmdlet.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-RemoveVM [<SwitchParameter>]

Specifies the guests on each node should be removed from IMDS Attestation before disabling on cluster.

Disable cannot continue before guests are removed.

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Force [<SwitchParameter>]

No confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (https:/go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

System.Management.Automation.PSObject

----- EXAMPLE 1 -----

RELATED LINKS

https://learn.microsoft.com/powershell/module/az.stackhci/disable-azstackhciattestation