



Windows PowerShell Get-Help on Cmdlet 'Disable-AzStorageStaticWebsite'

PS:\>Get-HELP Disable-AzStorageStaticWebsite -Full

NAME

Disable-AzStorageStaticWebsite

SYNOPSIS

Disable static website for the Azure Storage account.

SYNTAX

```
Disable-AzStorageStaticWebsite [-Context  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>] [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]  
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Disable-AzStorageStaticWebsite cmdlet disables static website for the Azure Storage account.

PARAMETERS

-Context <Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>

Azure Storage Context Object

Required? false
Position? named
Default value None
Accept pipeline input? True (ByPropertyName, ByValue)
Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

{{Fill PassThru Description}}

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext

OUTPUTS

Microsoft.WindowsAzure.Commands.Storage.Model.ResourceModel.PSStaticWebsiteProperties

NOTES

Disable-AzStorageStaticWebsite

This command disables static website for a Azure Storage account.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/disable-azstoragestaticwebsite>