



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Disable-RunspaceDebug'

PS:\>Get-HELP Disable-RunspaceDebug -Full

NAME

Disable-RunspaceDebug

SYNOPSIS

Disables debugging on one or more runspaces, and releases any pending debugger stop.

SYNTAX

Disable-RunspaceDebug [-ProcessName] <System.String> [-AppDomainName] <System.String[]>

[<CommonParameters>]

Disable-RunspaceDebug [-Runspace] <System.Management.Automation.Runspaces.Runspace[]>

[<CommonParameters>]

Disable-RunspaceDebug [-RunspaceId] <System.Int32[]> [<CommonParameters>]

Disable-RunspaceDebug [-RunspaceInstanceId] <System.Guid[]> [<CommonParameters>]

Disable-RunspaceDebug [-RunspaceName] <System.String[]> [<CommonParameters>]

DESCRIPTION

The `Disable-RunspaceDebug` cmdlet disables debugging on one or more runspaces, and releases any pending debugger stop.

PARAMETERS

-AppDomainName <System.String[]>

The name of the application domain that hosts the PowerShell runspace.

Required? false

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ProcessName <System.String>

The name of the process that hosts the PowerShell runspace.

Required? false

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Runspace <System.Management.Automation.Runspaces.Runspace[]>

One or more Runspace objects to be disabled.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-RunspaceId <System.Int32[]>

One or more Runspace Id numbers to be disabled.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RunspaceInstanceId <System.Guid[]>

One or more Runspace GUIDs to be disabled.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RunspaceName <System.String[]>

One or more Runspace names to be disabled.

Required? false

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

NOTES

----- 1: Disable the default runspace debugger -----

Disable-RunspaceDebug

Get-RunspaceDebug

Id	Name	Enabled	BreakAll
1	Runspace1	False	False

RELATED LINKS

https://learn.microsoft.com/powershell/module/microsoft.powershell.utility/disable-runspacedebug?view=powershell-5.1&WT.mc_id=ps-gethelp Online Version:

Enable-RunspaceDebug

Get-RunspaceDebug