



Windows PowerShell Get-Help on Cmdlet 'Disable-StorageDataCollection'

PS:\>Get-HELP Disable-StorageDataCollection -Full

NAME

Disable-StorageDataCollection

SYNTAX

Disable-StorageDataCollection -PhysicalDisk <CimInstance#MSFT_PhysicalDisk> -StorageDataCollectionType {StorageIoDistribution} [<CommonParameters>]

Disable-StorageDataCollection -DeviceGuid <string> -StorageDataCollectionType {StorageIoDistribution} [<CommonParameters>]

Disable-StorageDataCollection -DeviceNumber <string> -StorageDataCollectionType {StorageIoDistribution} [<CommonParameters>]

PARAMETERS

-DeviceGuid <string>

Required? true

Position? Named

Accept pipeline input? false

Parameter set name ByDeviceGuid

Aliases DeviceId

Dynamic? false

-DeviceNumber <string>

Required? true

Position? Named

Accept pipeline input? false

Parameter set name ByDeviceNumber

Aliases None

Dynamic? false

-PhysicalDisk <CimInstance#MSFT_PhysicalDisk>

Required? true

Position? Named

Accept pipeline input? true (ByValue)

Parameter set name ByPhysicalDisk

Aliases None

Dynamic? false

-StorageDataCollectionType <StorageDataCollectionType>

Required? true

Position? Named

Accept pipeline input? false

Parameter set name ByDeviceNumber, ByDeviceGuid, ByPhysicalDisk

Aliases None

Dynamic? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Management.Infrastructure.CimInstance

OUTPUTS

System.Object

ALIASES

None

REMARKS

Get-Help cannot find the Help files for this cmdlet on this computer. It is displaying only partial help.

-- To download and install Help files for the module that includes this cmdlet, use Update-Help.