



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Enable-AppvClientConnectionGroup'

PS C:\Users\wahid> Get-Help Enable-AppvClientConnectionGroup

NAME

Enable-AppvClientConnectionGroup

SYNOPSIS

Enables a running connection group on the computer running the App-V client.

SYNTAX

```
Enable-AppvClientConnectionGroup [-ConnectionGroup]
<AppvClientConnectionGroup> [-Global] [-UserSID <String>] [<CommonParameters>]
```

```
Enable-AppvClientConnectionGroup [-GroupId] <Guid> [-VersionId] <Guid>
[-Global] [-UserSID <String>] [<CommonParameters>]
```

```
Enable-AppvClientConnectionGroup [-Name] <String> [-Global] [-UserSID
<String>] [<CommonParameters>]
```

DESCRIPTION

The Enable-AppvClientConnectionGroup cmdlet enables a connection group to the computer that runs the Microsoft Application Virtualization (App-V) client.

PARAMETERS

-ConnectionGroup <AppvClientConnectionGroup>

Specifies an App-V Connection Group object.

-Global [<SwitchParameter>]

Indicates that this cmdlet enables the connection group is disabled for all users that log into the target computer. Otherwise, it enables the connection group only for the currently running user.

-GroupId <Guid>

Specifies the ID associated with a connection group.

-Name <String>

Specifies the name of the App-V connection group.

-UserSID <String>

Specifies the SID of the intended user, in the form of S-1-2-34-56789012-3456789012-345678901-2345. This parameter requires elevated rights to run.

-VersionId <Guid>

Specifies a GUID that differentiates a connection group version from other versions. If you do not specify this parameter, the cmdlet operates on all versions of the connection group.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

---- Example 1: Enable a connection group by using its name ----

```
PS C:\> Enable-AppvClientConnectionGroup -Name "MyGroup" -Global
```

This command enables the connection group named MyGroup to all users on the computer.

----- Example 2: Enable a connection group by using its ID -----

```
PS C:\> Enable-AppvClientConnectionGroup -GroupID  
35ec9e5f-ab21-463f-8fe6-b90d4b66d182
```

This command enables the connection group that has the group ID 35ec9e5f-ab21-463f-8fe6-b90d4b66d182.

Example 3: Enable all connection groups by names that match a string

```
PS C:\> Get-AppvClientConnectionGroup -Name "MyGr*" |  
Enable-AppvClientConnectionGroup
```

This command finds all connection groups that have the string MyGr in the name, and then enables them.

REMARKS

To see the examples, type: "get-help Enable-AppvClientConnectionGroup -examples".

For more information, type: "get-help Enable-AppvClientConnectionGroup -detailed".

For technical information, type: "get-help Enable-AppvClientConnectionGroup -full".

For online help, type: "get-help Enable-AppvClientConnectionGroup -online"