



windows PowerShell Get-Help on Cmdlet 'Enable-AzNetworkCloudStorageApplianceRemoteVendorManagement'

PS: \>Get-HELP Enable-AzNetworkCloudStorageApplianceRemoteVendorManagement -Full

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

WARNING: The names of some imported commands from the module 'Az.NetworkCloud.private' include unapproved verbs that might make them less discoverable. To find the

commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Enable-AzNetworkCloudStorageApplianceRemoteVendorManagement

SYNOPSIS

Enable remote vendor management of the provided storage appliance.

SYNTAX

```

Enable-AzNetworkCloudStorageApplianceRemoteVendorManagement -ResourceGroupName <String>
-StorageApplianceName <String> [-SubscriptionId <String>] [-SupportEndpoint
    <String[]>] [-DefaultProfile <PSObject>] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru]
    [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]
[<CommonParameters>]

```

```

Enable-AzNetworkCloudStorageApplianceRemoteVendorManagement -InputObject <INetworkCloudIdentity>
[-SupportEndpoint <String[]>] [-DefaultProfile <PSObject>] [-AsJob]
    [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru]
[-Proxy <Uri>] [-ProxyCredential <PSCredential>]
    [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

```

DESCRIPTION

Enable remote vendor management of the provided storage appliance.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-StorageApplianceName <String>

The name of the storage appliance.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

The value must be an UUID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <INetworkCloudIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-SupportEndpoint <String[]>

Field Deprecated.

This field is not used and will be rejected if provided.

The list of IPv4 subnets (in CIDR format), IPv6 subnets (in CIDR format), or hostnames that the storage appliance needs accessible in order to turn on the remote vendor management.

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.
Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.NetworkCloud.Models.INetworkCloudIdentity

OUTPUTS

System.Boolean

NOTES

COMPLEX PARAMETER PROPERTIES

information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <INetworkCloudIdentity>: Identity Parameter

[AgentPoolName <String>]: The name of the Kubernetes cluster agent pool.

[BareMetalMachineKeySetName <String>]: The name of the bare metal machine key set.

[BareMetalMachineName <String>]: The name of the bare metal machine.

[BmcKeySetName <String>]: The name of the baseboard management controller key set.

[CloudServicesNetworkName <String>]: The name of the cloud services network.

[ClusterManagerName <String>]: The name of the cluster manager.

[ClusterName <String>]: The name of the cluster.

[ConsoleName <String>]: The name of the virtual machine console.

[Id <String>]: Resource identity path

[KubernetesClusterName <String>]: The name of the Kubernetes cluster.

[L2NetworkName <String>]: The name of the L2 network.

[L3NetworkName <String>]: The name of the L3 network.

[MetricsConfigurationName <String>]: The name of the metrics configuration for the cluster.

[RackName <String>]: The name of the rack.

[RackSkuName <String>]: The name of the rack SKU.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[StorageApplianceName <String>]: The name of the storage appliance.

[SubscriptionId <String>]: The ID of the target subscription. The value must be an UUID.

[TrunkedNetworkName <String>]: The name of the trunked network.

[VirtualMachineName <String>]: The name of the virtual machine.

[VolumeName <String>]: The name of the volume.

----- EXAMPLE 1 -----

```
PS C:\>Enable-AzNetworkCloudStorageApplianceRemoteVendorManagement -ResourceGroupName
resourceGroupName -StorageApplianceName storageApplianceName -SubscriptionId
subscriptionId
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.networkcloud/enable-aznetworkcloudstorageappliance-remote-vendor-management>