



Windows PowerShell Get-Help on Cmdlet 'Enable-AzStorageBlobLastAccessTimeTracking'

PS:\>Get-HELP Enable-AzStorageBlobLastAccessTimeTracking -Full

NAME

Enable-AzStorageBlobLastAccessTimeTracking

SYNOPSIS

Enable last access time tracking for the Azure Storage Blob service.

SYNTAX

```

Enable-AzStorageBlobLastAccessTimeTracking [-ResourceGroupName] <System.String> [-StorageAccountName]
<System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]

Enable-AzStorageBlobLastAccessTimeTracking [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
    -StorageAccount <Microsoft.Azure.Commands.Management.Storage.Models.PSStorageAccount> [-Confirm] [-WhatIf]
    [<CommonParameters>]

```

The Enable-AzStorageBlobLastAccessTimeTracking cmdlet enables last access time tracking for the Azure Storage Blob service.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Display ServiceProperties

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-StorageAccount <Microsoft.Azure.Commands.Management.Storage.Models.PSStorageAccount>

Storage account object

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-StorageAccountName <System.String>

Storage Account Name.

Required? true
Position? 1
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Management.Storage.Models.PSStorageAccount

OUTPUTS

Microsoft.Azure.Commands.Management.Storage.Models.PSRestorePolicy

NOTES

Example 1: Enable last access time tracking for the Blob service

```
Enable-AzStorageBlobLastAccessTimeTracking -ResourceGroupName "myresourcegroup" -AccountName "mystorageaccount" -PassThru
```

Enable	Name	TrackingGranularityInDays	BlobType
-----	-----	-----	-----
True	AccessTimeTracking	1	{blockBlob}

This command enables last access time tracking for the Blob service, and show the last access time tracking policy

properties.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/enable-azstoragebloblastaccesstimetracking>