



Windows PowerShell Get-Help on Cmdlet 'Export-StartLayout'

PS:\>Get-HELP Export-StartLayout -Full

NAME

Export-StartLayout

SYNOPSIS

Exports the layout of the Start screen.

SYNTAX

Export-StartLayout [-Confirm] -LiteralPath <String> [-UseDesktopApplicationID] [-WhatIf] [<CommonParameters>]

Export-StartLayout [-Path] <String> [-Confirm] [-UseDesktopApplicationID] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Export-StartLayout cmdlet exports the layout of the tiles on Start of the current user. You can export layout and use Import-StartLayout as well as other

management policies for the Start layout. Specify the .xml file name extension in the name of the file.

PARAMETERS

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-LiteralPath <String>

Specifies a literal path to a layout file. Include the file .xml file name extension. This parameter does not accept the wildcard character (*). If the path

includes an escape character (\), enclose the string in single quotes (').

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Path <String>

Specifies an absolute path to a layout file.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-UseDesktopApplicationID [<SwitchParameter>]

Specifies that the layout file should export the DesktopApplicationID value instead of DesktopApplicationLinkPath which is the default. DesktopApplicationID is

the application's ID and DesktopApplicationLinkPath is a path to a shortcut link (.lnk file) to a Windows desktop

application.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Enum

You can specify the following file format:

- XML. Export as an .xml file.

OUTPUTS

NOTES

----- Example 1: Export the layout -----

```
PS C:\> Export-StartLayout -Path "C:\Layouts\Marketing.xml"
```

This command exports the layout of the tiles on Start to a file named Marketing.xml in the C:\Layouts folder.

RELATED LINKS

Online

Version:

https://learn.microsoft.com/powershell/module/startlayout/export-startlayout?view=windowsserver2022-ps&wt.mc_id=ps-gethelp

Export-StartLayoutEdgeAssets

Import-StartLayout