



Windows PowerShell Get-Help on Cmdlet 'Get-AzADAppPermission'

PS:\>Get-HELP Get-AzADAppPermission -Full

NAME

Get-AzADAppPermission

SYNOPSIS

Lists API permissions the application has requested.

SYNTAX

```
Get-AzADAppPermission -ObjectId <Guid> [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend  
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential  
<PSCredential>] [-ProxyUseDefaultCredentials] [-DefaultProfile <PSObject>] [<CommonParameters>]
```

```
Get-AzADAppPermission [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>]  
[-Proxy <Uri>] [-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] -ApplicationId <Guid> [-DefaultProfile <PSObject>] [<CommonParameters>]
```

DESCRIPTION

Lists API permissions the application has requested.

PARAMETERS

-ObjectId <Guid>

The object Id of application.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-ApplicationId <Guid>

The application Id.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Resources.MSGraph.Models.MicrosoftGraphApplicationApiPermission

----- EXAMPLE 1 -----

PS C:\>Get-AzADAppPermission -ObjectId 18797549-86a9-4906-b2a9-54f08cd3c427

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.resources/get-azadapppermission>