



Windows PowerShell Get-Help on Cmdlet 'Get-AzADServicePrincipalAppRoleAssignment'

PS:\>Get-HELP Get-AzADServicePrincipalAppRoleAssignment -Full

NAME

Get-AzADServicePrincipalAppRoleAssignment

SYNOPSIS

Get appRoleAssignments from servicePrincipals

SYNTAX

```
Get-AzADServicePrincipalAppRoleAssignment -ServicePrincipalId <String> [-Expand <String[]>] [-Select <String[]>]
[-Count] [-Filter <String>] [-Orderby <String[]>]
[-Search <String>] [-First <UInt64>] [-Skip <UInt64>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

```
Get-AzADServicePrincipalAppRoleAssignment -ServicePrincipalId <String> -AppRoleAssignmentId <String> [-Expand
<String[]>] [-Select <String[]>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy
<Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Get appRoleAssignments from servicePrincipals

PARAMETERS

-ServicePrincipalId <String>

key: id of servicePrincipal

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AppRoleAssignmentId <String>

key: id of appRoleAssignment

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Expand <String[]>

Expand related entities

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Select <String[]>

Select properties to be returned

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Count [<SwitchParameter>]

Include count of items

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Filter <String>

Filter items by property values

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-OrderBy <String[]>

Order items by property values

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Search <String>

Search items by search phrases

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-First <UInt64>

Gets only the first 'n' objects.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-Skip <UInt64>

Ignores the first 'n' objects and then gets the remaining objects.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Resources.MSGraph.Models.ApiV10.IMicrosoftGraphAppRoleAssignment

----- EXAMPLE 1 -----

```
PS C:\>Get-AzADServicePrincipalAppRoleAssignment -ServicePrincipalId 71beb965-8347-495d-a589-c21cdde7a722
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzADServicePrincipalAppRoleAssignment -ServicePrincipalId 71beb965-8347-495d-a589-c21cdde7a722  
-AppRoleAssignmentId  
Zbm-cUeDXUmliclc3eenlkgIm8kv9kJPj4MFhepACNE
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.resources/get-azadserviceprincipalapproleassignment>