



Windows PowerShell Get-Help on Cmdlet 'Get-AzAdvisorConfiguration'

PS:\>Get-HELP Get-AzAdvisorConfiguration -Full

NAME

Get-AzAdvisorConfiguration

SYNOPSIS

Retrieve Azure Advisor configurations and also retrieve configurations of contained resource groups.

SYNTAX

```
Get-AzAdvisorConfiguration [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

```
Get-AzAdvisorConfiguration [-SubscriptionId <String[]>] -ResourceGroupName <String> [-DefaultProfile <PSObject>]
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Retrieve Azure Advisor configurations and also retrieve configurations of contained resource groups.

PARAMETERS

-SubscriptionId <String[]>

The Azure subscription ID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the Azure resource group.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Advisor.Models.Api202001.IConfigData

```
PS C:\>Get-AzAdvisorConfiguration
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzAdvisorConfiguration -ResourceGroupName Inxtest
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.advisor/get-azadvisorconfiguration>