



Windows PowerShell Get-Help on Cmdlet 'Get-AzAksNodePoolUpgradeProfile'

PS:\>Get-HELP Get-AzAksNodePoolUpgradeProfile -Full

NAME

Get-AzAksNodePoolUpgradeProfile

SYNOPSIS

Gets the upgrade profile for an agent pool.

SYNTAX

```
Get-AzAksNodePoolUpgradeProfile -ClusterName <String> -NodePoolName <String> -ResourceGroupName <String>
[-SubscriptionId <String>] [-DefaultProfile <PSObject>]
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]

Get-AzAksNodePoolUpgradeProfile -InputObject <IAksIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

DESCRIPTION

Gets the upgrade profile for an agent pool.

PARAMETERS

-ClusterName <String>

The name of the managed cluster resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NodePoolName <String>

The name of the agent pool.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IAksIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Aks.Models.IAksIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Aks.Models.Api20230201.IAgentPoolUpgradeProfile

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <IAksIdentity>: Identity Parameter

[AgentPoolName <String>]: The name of the agent pool.

[CommandId <String>]: Id of the command.

[ConfigName <String>]: The name of the maintenance configuration.

[Id <String>]: Resource identity path

[Location <String>]: The name of Azure region.

[PrivateEndpointConnectionName <String>]: The name of the private endpoint connection.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[ResourceName <String>]: The name of the managed cluster resource.

[RoleName <String>]: The name of the role for managed cluster accessProfile resource.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzAksNodePoolUpgradeProfile -ResourceGroupName group -ClusterName myCluster -AgentPoolName default
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.aks/get-azaksnodepoolupgradeprofile>

