



Windows PowerShell Get-Help on Cmdlet 'Get-AzAppConfigurationKey'

PS: \>Get-HELP Get-AzAppConfigurationKey -Full

NAME

Get-AzAppConfigurationKey

SYNOPSIS

Gets a list of keys.

SYNTAX

```
Get-AzAppConfigurationKey -Endpoint <String> [-After <String>] [-Name <String>] [-AcceptDatetime <String>]
[-SyncToken <String>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]&;] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

DESCRIPTION

Gets a list of keys.

PARAMETERS

-Endpoint <String>

The endpoint of the App Configuration instance to send requests to.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-After <String>

Instructs the server to return elements that appear after the element referred to by the specified token.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Name <String>

A filter for the name of the returned keys.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AcceptDatetime <String>

Requests the server to respond with the state of the resource at the specified time.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SyncToken <String>

Used to guarantee real-time consistency between requests.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.AppConfigurationdata.Models.IKey

----- EXAMPLE 1 -----

PS C:\>Get-AzAppConfigurationKey -Endpoint \$endpoint

----- EXAMPLE 2 -----

```
PS C:\>Get-AzAppConfigurationKey -Endpoint $endpoint -Name key*
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.appconfiguration/get-azappconfigurationkey>