



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Get-AzApplicationGatewayAvailableServerVariableAndHeader'

PS:\>Get-HELP Get-AzApplicationGatewayAvailableServerVariableAndHeader -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Get-AzApplicationGatewayAvailableServerVariableAndHeader

SYNOPSIS

Get the supported server variables and available request and response headers.

SYNTAX

```
Get-AzApplicationGatewayAvailableServerVariableAndHeader [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>  
[-RequestHeader] [-ResponseHeader] [-ServerVariable] [<CommonParameters>]
```

DESCRIPTION

The Get-AzApplicationGatewayAvailableServerVariableAndHeader cmdlet gets the supported server variables and available request and response headers. Parameters can be

used to get the variables or headers lists.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RequestHeader <System.Management.Automation.SwitchParameter>

Application Gateway available request headers.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResponseHeader <System.Management.Automation.SwitchParameter>

Application Gateway available response headers.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ServerVariable <System.Management.Automation.SwitchParameter>

Application Gateway available server variables.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSApplicationGatewayAvailableServerVariableAndRequestHeaderResult

NOTES

List-AzApplicationGatewayAvailableServerVariableAndHeader is an alias for the Get-AzApplicationGatewayAvailableServerVariableAndHeader cmdlet.

----- Example 1 -----

Get-AzApplicationGatewayAvailableServerVariableAndHeader -ServerVariable

This commands returns all the available server variables.

----- Example 2 -----

Get-AzApplicationGatewayAvailableServerVariableAndHeader -RequestHeader

This commands returns all the available request headers.

----- Example 3 -----

Get-AzApplicationGatewayAvailableServerVariableAndHeader -ResponseHeader

This commands returns all the available response headers.

----- Example 4 -----

Get-AzApplicationGatewayAvailableServerVariableAndHeader -ServerVariable -RequestHeader -ResponseHeader

This commands returns all the available server variables, request and response headers.

----- Example 5 -----

Get-AzApplicationGatewayAvailableServerVariableAndHeader

This commands returns all the available server variables, request and response headers.

<https://learn.microsoft.com/powershell/module/az.network/get-azapplicationgatewayavailableservervariableandheader>