



Windows PowerShell Get-Help on Cmdlet 'Get-AzApplicationGatewayTrustedRootCertificate'

PS:\>Get-HELP Get-AzApplicationGatewayTrustedRootCertificate -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Get-AzApplicationGatewayTrustedRootCertificate

SYNOPSIS

Gets the Trusted Root Certificate with a specific name from the Application Gateway.

SYNTAX

```
Get-AzApplicationGatewayTrustedRootCertificate [-ApplicationGateway
<Microsoft.Azure.Commands.Network.Models.PSApplicationGateway> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>] [<CommonParameters>]
```

DESCRIPTION

The Get-AzApplicationGatewayTrustedRootCertificate cmdlet gets Trusted Root Certificate with a specific name from the

Application Gateway.

PARAMETERS

-ApplicationGateway <Microsoft.Azure.Commands.Network.Models.PSApplicationGateway>

The applicationGateway

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the TrustedRoot certificate

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSApplicationGateway

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSApplicationGatewayTrustedRootCertificate

NOTES

----- Example 1 -----

```
$gw = Get-AzApplicationGateway -Name $appgwName -ResourceGroupName $resgpName
```

```
$trustedRootCert = Get-AzApplicationGatewayTrustedRootCertificate -ApplicationGateway $gw -Name $certName
```

The first command gets the Application Gateway and stores it in \$gw variable. The second command gets the Trusted Root Certificate with a specified name from the
Application Gateway.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/get-azapplicationgatewaytrustedrootcertificate>

Add-AzApplicationGatewayTrustedRootCertificate

New-AzApplicationGatewayTrustedRootCertificate

Remove-AzApplicationGatewayTrustedRootCertificate

Set-AzApplicationGatewayTrustedRootCertificate