



Windows PowerShell Get-Help on Cmdlet 'Get-AzAutomanageConfigProfileAssignment'

PS:\>Get-HELP Get-AzAutomanageConfigProfileAssignment -Full

NAME

Get-AzAutomanageConfigProfileAssignment

SYNOPSIS

Get information about a configuration profile assignment

SYNTAX

```
Get-AzAutomanageConfigProfileAssignment [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzAutomanageConfigProfileAssignment -ResourceGroupName <String> [-SubscriptionId <String[]>] -ClusterName
<String> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

Get-AzAutomanageConfigProfileAssignment -ResourceGroupName <String> [-SubscriptionId <String[]>] -MachineName <String>

```
<String> [-DefaultProfile <PSObject>] [-Break]
    [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
    [<CommonParameters>]
```

```
Get-AzAutomanageConfigProfileAssignment -ResourceGroupName <String> [-SubscriptionId <String[]>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend
    <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzAutomanageConfigProfileAssignment -ResourceGroupName <String> [-SubscriptionId <String[]>] -VMName
<String> [-DefaultProfile <PSObject>] [-Break]
    [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
    [<CommonParameters>]
```

```
Get-AzAutomanageConfigProfileAssignment -InputObject <IAutomanageIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
    [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Get information about a configuration profile assignment

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-VMName <String>

The name of the virtual machine.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IAutomanageIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-MachineName <String>

The name of the Arc machine.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ClusterName <String>

The name of the Arc machine.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Automanage.Models.IAutomanageIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Automanage.Models.Api20220504.IConfigurationProfileAssignment

NOTES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help about_Hash_Tables.

INPUTOBJECT <IAutomanageIdentity>: Identity Parameter

[BestPracticeName <String>]: The Automanage best practice name.

[ClusterName <String>]: The name of the Arc machine.

[ConfigurationProfileAssignmentName <String>]: Name of the configuration profile assignment. Only default is supported.

[ConfigurationProfileName <String>]: Name of the configuration profile.

[Id <String>]: Resource identity path

[MachineName <String>]: The name of the Arc machine.

[ReportName <String>]: The report name.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[SubscriptionId <String>]: The ID of the target subscription.

[VMName <String>]: The name of the virtual machine.

[VersionName <String>]: The Automanage best practice version name.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzAutomanageConfigProfileAssignment
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzAutomanageConfigProfileAssignment -ResourceGroupName automangerg
```

----- EXAMPLE 3 -----

```
PS C:\>Get-AzAutomanageConfigProfileAssignment -ResourceGroupName automangerg -VMName aglinuxvm
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.automanage/get-azautomanageconfigprofileassignment>