



Windows PowerShell Get-Help on Cmdlet 'Get-AzBatchLocationQuota'

PS: \>Get-HELP Get-AzBatchLocationQuota -Full

NAME

Get-AzBatchLocationQuota

SYNOPSIS

Gets the Batch service quotas for your subscription at the given location.

SYNTAX

```
Get-AzBatchLocationQuota [-Location] <System.String> [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>  
[<CommonParameters>]
```

DESCRIPTION

Gets the Batch service quotas for the specified subscription at the given location.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Location <System.String>

Specifies the region for which this cmdlet checks the quotas. For more information, see Azure Regions (<https://azure.microsoft.com/regions>).

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Batch.Models.PSBatchLocationQuotas

NOTES

Example 1: Get the Batch service quotas for the subscription in the West US region

```
Get-AzBatchLocationQuota -Location "westus"
```

AccountQuota Location

```
-----  
1      westus
```

This command gets the quotas for the current subscription in the West US region. The return value indicates that this subscription can create only one Batch account in that region.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.batch/get-azbatchlocationquota>