



Windows PowerShell Get-Help on Cmdlet 'Get-AzCapacityReservationGroup'

PS:\>Get-HELP Get-AzCapacityReservationGroup -Full

NAME

Get-AzCapacityReservationGroup

SYNOPSIS

Gets the properties of Capacity Reservation Groups

SYNTAX

```
Get-AzCapacityReservationGroup [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-InstanceView] [-Name
<System.String>] [-ResourceGroupName <System.String>] [<CommonParameters>]
```

```
Get-AzCapacityReservationGroup [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-InstanceView]
-ResourceId
<System.String> [<CommonParameters>]
```

DESCRIPTION

The Get-AzCapacityReservationGroup cmdlet gets the properties of Capacity Reservation resources from Azure.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InstanceView <System.Management.Automation.SwitchParameter>

Get the Instance View of the Capacity Reservation Group.

Required? false

Position? named

Default value False

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the capacity reservation group.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? true

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	true

-ResourceId <System.String>

Resource ID for the capacity reservation group.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

System.Management.Automation.SwitchParameter

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSCapacityReservationGroup

NOTES

----- Example 1 -----

```
Get-AzCapacityReservationGroup -ResourceGroupName $rgname -Name "CRGroup1" -InstanceView
```

This will retrieve the Capacity Reservation Group named "CRGroup1" with its instance view information.

----- Example 2 -----

```
Get-AzCapacityReservationGroup -ResourceGroupName $rgname
```

This will retrieve all the Capacity Reservation Groups' information from resource group.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/get-azcapacityreservationgroup>