



Windows PowerShell Get-Help on Cmdlet 'Get-AzCdnEdgeNode'

PS:\>Get-HELP Get-AzCdnEdgeNode -Full

NAME

Get-AzCdnEdgeNode

SYNOPSIS

Edgenodes are the global Point of Presence (POP) locations used to deliver CDN content to end users.

SYNTAX

```
Get-AzCdnEdgeNode [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Edgenodes are the global Point of Presence (POP) locations used to deliver CDN content to end users.

PARAMETERS

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Cdn.Models.Api20240201.EdgeNode

----- EXAMPLE 1 -----

PS C:\>Get-AzCdnEdgeNode

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.cdn/get-azcdnedgenode>