



Windows PowerShell Get-Help on Cmdlet 'Get-AzCognitiveServicesCommitmentTier'

PS: \>Get-HELP Get-AzCognitiveServicesCommitmentTier -Full

NAME

Get-AzCognitiveServicesCommitmentTier

SYNOPSIS

Get CommitmentTier of Cognitive Services

SYNTAX

Get-AzCognitiveServicesCommitmentTier [-Location] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>
[<CommonParameters>]

DESCRIPTION

Get CommitmentTier of Cognitive Services

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Location <System.String>

Cognitive Services Account Location.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Management.CognitiveServices.Models.CommitmentTier

----- Example 1 -----

Get-AzCognitiveServicesCommitmentTier -Location 'WestUS'

Kind : kind

SkuName : sku

HostingModel : hosting model

PlanType : plan type

Tier : tier

MaxCount :

Quota : Microsoft.Azure.Management.CognitiveServices.Models.CommitmentQuota

Cost : Microsoft.Azure.Management.CognitiveServices.Models.CommitmentCost

Get CommitmentTier of Cognitive Services

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.cognitiveservices/get-azcognitiveservicescommitmenttier>