



Windows PowerShell Get-Help on Cmdlet 'Get-AzConfidentialLedger'

PS:\>Get-HELP Get-AzConfidentialLedger -Full

NAME

Get-AzConfidentialLedger

SYNOPSIS

Retrieves the properties of a Confidential Ledger.

SYNTAX

```
Get-AzConfidentialLedger [-SubscriptionId <String[]>] [-Filter <String>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzConfidentialLedger -Name <String> -ResourceGroupName <String> [-SubscriptionId <String[]>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzConfidentialLedger -ResourceGroupName <String> [-SubscriptionId <String[]>] [-Filter <String>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend
```

<SendAsyncStep[]> [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]

Get-AzConfidentialLedger -InputObject <IConfidentialLedgerIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]

DESCRIPTION

Retrieves the properties of a Confidential Ledger.

PARAMETERS

-Name <String>

Name of the Confidential Ledger

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The Azure subscription ID.

This is a GUID-formatted string (e.g.

00000000-0000-0000-0000-000000000000)

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IConfidentialLedgerIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-Filter <String>

The filter to apply on the list operation.

eg.

\$filter=ledgerType eq 'Public'

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.ConfidentialLedger.Models.IConfidentialLedgerIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ConfidentialLedger.Models.Api20220513.IConfidentialLedger

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <IConfidentialLedgerIdentity>: Identity Parameter

[Id <String>]: Resource identity path

[LedgerName <String>]: Name of the Confidential Ledger

[ResourceGroupName <String>]: The name of the resource group.

[SubscriptionId <String>]: The Azure subscription ID. This is a GUID-formatted string (e.g. 00000000-0000-0000-0000-000000000000)

----- EXAMPLE 1 -----

PS C:\>Get-AzConfidentialLedger `

-SubscriptionId 00000000-0000-0000-0000-000000000000

----- EXAMPLE 2 -----

```
PS C:\>Get-AzConfidentialLedger `
```

```
-Name test-ledger `
```

```
-ResourceGroupName test-rg
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.confidentialledger/get-azconfidentialledger>