



Windows PowerShell Get-Help on Cmdlet 'Get-AzConfigurationAssignment'

PS:\>Get-HELP Get-AzConfigurationAssignment -Full

NAME

Get-AzConfigurationAssignment

SYNOPSIS

List configurationAssignments for resource.

SYNTAX

```
Get-AzConfigurationAssignment [[-ResourceGroupName] <System.String>] [[-ProviderName] <System.String>]
[[-ResourceType] <System.String>] [[-ResourceName]
<System.String>] [-ConfigurationAssignmentName <System.String>] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-ResourceParentName <System.String>] [-ResourceParentType <System.String>]
[<CommonParameters>]
```

DESCRIPTION

List configurationAssignments for resource.

PARAMETERS

-ConfigurationAssignmentName <System.String>

The configuration assignment name.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ProviderName <System.String>

The resource provider Name.

Required? false

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource Group Name.

Required? false

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceName <System.String>

The resource name.

Required? false

Position? 3

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceParentName <System.String>

The parent resource name.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceParentType <System.String>

The parent resource type.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceType <System.String>

The resource type.

Required? false
Position? 2
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Maintenance.Models.PSConfigurationAssignment

NOTES

----- Example 1 -----

```
Get-AzConfigurationAssignment -ResourceGroupName smdtest$location -ResourceParentType hostGroups  
-ResourceParentName smddhg$location -ResourceType hosts -ResourceName  
smddh$location -ProviderName Microsoft.Compute
```

MaintenanceConfigurationId :

/subscriptions/42c974dd-2c03-4f1b-96ad-b07f050aaa74/resourcegroups/ps1/providers/Microsoft.Maintenance/maintenance
Configurations/ps2

Id :

/subscriptions/42c974dd-2c03-4f1b-96ad-b07f050aaa74/resourcegroups/smdtestwestus2/providers/Microsoft.Compute/host
Groups/smdhghwestus2/hosts/smdhghwestus2/providers/Mic
rosoft.Maintenance/configurationAssignments/ps2

Name : ps2

Type : Microsoft.Maintenance/configurationAssignments

List configurationAssignments for dedicated host.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.maintenance/get-azconfigurationassignment>