



Windows PowerShell Get-Help on Cmdlet 'Get-AzContainerAppAvailableWorkloadProfile'

PS:\>Get-HELP Get-AzContainerAppAvailableWorkloadProfile -Full

NAME

Get-AzContainerAppAvailableWorkloadProfile

SYNOPSIS

Get all available workload profiles for a location.

SYNTAX

```
Get-AzContainerAppAvailableWorkloadProfile -Location <String> [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>]
[-Break] [-HttpPipelineAppend
    <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzContainerAppAvailableWorkloadProfile -InputObject <IApplIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
    [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Get all available workload profiles for a location.

PARAMETERS

-Location <String>

The name of Azure region.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IApplIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.App.Models.IAppIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.App.Models.IAvailableWorkloadProfile

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

`about_Hash_Tables`.

INPUTOBJECT <IAppIdentity>: Identity Parameter

[AuthConfigName <String>]: Name of the Container App AuthConfig.

[CertificateName <String>]: Name of the Certificate.

[ComponentName <String>]: Name of the Dapr Component.

[ConnectedEnvironmentName <String>]: Name of the connectedEnvironment.

[ContainerAppName <String>]: Name of the Container App.

[DetectorName <String>]: Name of the Container App Detector.

[EnvironmentName <String>]: Name of the Environment.

[Id <String>]: Resource identity path

[JobExecutionName <String>]: Job execution name.

[JobName <String>]: Job Name

[Location <String>]: The name of Azure region.

[ManagedCertificateName <String>]: Name of the Managed Certificate.

[ReplicaName <String>]: Name of the Container App Revision Replica.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[RevisionName <String>]: Name of the Container App Revision.

[SourceControlName <String>]: Name of the Container App SourceControl.

[StorageName <String>]: Name of the storage.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzContainerAppAvailableWorkloadProfile -Location eastus
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.app/get-azcontainerappavailableworkloadprofile>