



Windows PowerShell Get-Help on Cmdlet 'Get-AzCosmosDBAccountKey'

PS:\>Get-HELP Get-AzCosmosDBAccountKey -Full

NAME

Get-AzCosmosDBAccountKey

SYNOPSIS

Get Keys{"ConnectionKeys", "PrimaryReadOnly" or "Keys"} for the given CosmosDB Account.

SYNTAX

```

Get-AzCosmosDBAccountKey [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults> [-Type <System.String>]
[<CommonParameters>]

```

```

Get-AzCosmosDBAccountKey [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name <System.String>

-ResourceGroupName <System.String> [-Type <System.String>] [<CommonParameters>]

```

```

Get-AzCosmosDBAccountKey [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Resource

```

<System.String>

[-Type <System.String>] [<CommonParameters>]

DESCRIPTION

Get the list of connection keys.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

ResourceId of the resource.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Type <System.String>

Value from: {ConnectionStrings, Keys, ReadOnlyKeys}. Default is Keys.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountListConnectionStrings

Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountListKeysResult

Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountListReadOnlyKeysResult

NOTES

----- Example 1 -----

Get-AzCosmosDBAccountKey -ResourceGroupName rg1 -Name dbname -Type "ReadOnlyKeys"

Name	Value
------	-------

----	-----
------	-------

PrimaryReadOnlyMasterKey

qjw0ISW1WNN0BIVPeaI7Tm3H8uZ1h7ESQjxaUendxHmIUNQowVvcL84fTqeXoC2HFgyu8Zo1mCFEcg0jZJHPjA==

SecondaryReadOnlyMasterKey

9YRcTABuOHcKyHAKf0ImCeHsrcXu02aelD1g3wjXjIX8SU4s2WNIEB5htJoy3xqxNDqlyGfnq3dblLbrZDbesg==

Lists the keys for CosmosDB Account. The Key Type can be value from : ConnectionStrings, Keys and ReadOnlyKeys.
Default is Keys.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/get-azcosmosdbaccountkey>