



Windows PowerShell Get-Help on Cmdlet 'Get-AzCosmosDBGremlinDatabaseThroughput'

PS:\>Get-HELP Get-AzCosmosDBGremlinDatabaseThroughput -Full

NAME

Get-AzCosmosDBGremlinDatabaseThroughput

SYNOPSIS

Gets the throughput of a CosmosDB Gremlin Database.

SYNTAX

```
Get-AzCosmosDBGremlinDatabaseThroughput -AccountName <System.String> [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name  
<System.String> -ResourceGroupName <System.String>  
    [<CommonParameters>]
```



```
Get-AzCosmosDBGremlinDatabaseThroughput [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject  
    <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults> -Name <System.String>  
    [<CommonParameters>]
```

The Get-AzCosmosDBGremlinDatabaseThroughput cmdlet gets the throughput of a CosmosDB Gremlin Database.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Database name.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-ResourceGroupName <System.String>

Name of resource group.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSThroughputSettingsGetResults

----- Example 1 -----

```
Get-AzCosmosDBGremlinDatabaseThroughput -ResourceGroupName "rgName" -AccountName "accountName" -Name  
"databaseName"
```

Name: {throughputName}

Id: {Id}

Throughput: {value}

MinimumThroughput: {value}

OfferReplacePending: {value}

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/get-azcosmosdbgremlindatabasethroughput>