



Windows PowerShell Get-Help on Cmdlet 'Get-AzCosmosDBRestorableDatabaseAccount'

PS:\>Get-HELP Get-AzCosmosDBRestorableDatabaseAccount -Full

NAME

Get-AzCosmosDBRestorableDatabaseAccount

SYNOPSIS

Gets the restorable database account object

SYNTAX

```
Get-AzCosmosDBRestorableDatabaseAccount [-DatabaseAccountInstanceId <System.String>] [-DatabaseAccountName  
<System.String>] [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Location  
<System.String>] [<CommonParameters>]
```

DESCRIPTION

Gets the list of all restorable database account objects in the given account, or a specific restorable database account object with the given instanceId and location

-DatabaseAccountInstanceId <System.String>

The instance Id of the CosmosDB database account.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DatabaseAccountName <System.String>

Name of the Cosmos DB database account.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Location <System.String>

Name of the Location in string.

Required? false

Position? named

Default value None

Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Management.CosmosDB.Models.PSRestorableDatabaseAccountGetResult

NOTES

----- Example 1 -----

Get-AzCosmosDBRestorableDatabaseAccount

Id :

/subscriptions/{subscriptionId}/providers/Microsoft.DocumentDB/locations/westus/restorableDatabaseAccounts/fb8f230e-ba
b0-452b-81cf-e32643ccc898

DatabaseAccountInstanceId : fb8f230e-bab0-452b-81cf-e32643ccc898

Location : West US
DatabaseAccountName : deleted-account-1
CreationTime : 8/2/2020 10:23:00 PM
DeletionTime : 8/2/2020 10:26:13 PM
OldestRestorableTime : 8/2/2020 10:23:00 PM
ApiType : Sql
RestorableLocations : {West US, East US}

Id :

/subscriptions/{subscriptionId}/providers/Microsoft.DocumentDB/locations/eastus/restorableDatabaseAccounts/ff921125-e31c-4e8c-ae0a-20fe719baca6

DatabaseAccountInstanceId : ff921125-e31c-4e8c-ae0a-20fe719baca6
Location : East US
DatabaseAccountName : deleted-account-2
CreationTime : 8/2/2020 6:32:32 PM
DeletionTime : 8/2/2020 6:34:48 PM
OldestRestorableTime : 8/2/2020 6:32:32 PM
ApiType : Sql
RestorableLocations : {Australia Southeast, East US, West US}

Id :

/subscriptions/{subscriptionId}/providers/Microsoft.DocumentDB/locations/westus/restorableDatabaseAccounts/c7b27ad9-3bc0-4955-8cc2-a81790e5c3b3

DatabaseAccountInstanceId : c7b27ad9-3bc0-4955-8cc2-a81790e5c3b3
Location : West US
DatabaseAccountName : live-account-1
CreationTime : 8/2/2020 6:34:35 PM
DeletionTime :
OldestRestorableTime : 8/2/2020 6:34:35 PM
ApiType : MongoDB
RestorableLocations : {West US}

Lists all the restorable database accounts in the current subscription

----- Example 1 -----

```
Get-AzCosmosDBRestorableDatabaseAccount -Location "West US" -DatabaseAccountInstanceId  
fb8f230e-bab0-452b-81cf-e32643ccc898
```

Id :

/subscriptions/{subscriptionId}/providers/Microsoft.DocumentDB/locations/westus/restorableDatabaseAccounts/fb8f230e-ba
b0-452b-81cf-e32643ccc898

DatabaseAccountInstanceId : fb8f230e-bab0-452b-81cf-e32643ccc898

Location : West US

DatabaseAccountName : deleted-account-1

CreationTime : 8/2/2020 10:23:00 PM

DeletionTime : 8/2/2020 10:26:13 PM

OldestRestorableTime : 8/2/2020 10:23:00 PM

ApiType : Sql

RestorableLocations : {West US, East US}

Gets the restorable database account with the given DatabaseInstanceId in the given ARM location

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/get-azcosmosdbrestorabledatabaseaccount>