



Windows PowerShell Get-Help on Cmdlet 'Get-AzCosmosDBSqlContainerThroughput'

PS:\>Get-HELP Get-AzCosmosDBSqlContainerThroughput -Full

NAME

Get-AzCosmosDBSqlContainerThroughput

SYNOPSIS

Gets the throughput settings corresponding to a CosmosDB Sql Container.

SYNTAX

```
Get-AzCosmosDBSqlContainerThroughput -AccountName <System.String> -DatabaseName <System.String>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>] -ResourceGroupName <System.String>
[<CommonParameters>]
```

```
Get-AzCosmosDBSqlContainerThroughput [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
    <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlContainerGetResults> [-Name <System.String>]
[<CommonParameters>]
```

DESCRIPTION

The Get-AzCosmosDBSqlContainerThroughput cmdlet gets the throughput settings corresponding to a CosmosDB Sql Container.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DatabaseName <System.String>

Database name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlContainerGetResults>

Sql Container object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Container name.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSThroughputSettingsGetResults

NOTES

----- Example 1 -----

```
Get-AzCosmosDBSqlContainerThroughput -AccountName "accountName" -ResourceGroupName  
"resourceGroupName" -DatabaseName "databaseName" -Name "containerName"
```

Throughput : {throughputValue}

MinimumThroughput :

OfferReplacePending :

Id :

Name : {Name}

Type : Microsoft.DocumentDB/databaseAccounts/sqlDatabases/containers/throughputSettings

Location :

Tags :

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/get-azcosmosdbsqlcontainerthroughput>