



Windows PowerShell Get-Help on Cmdlet 'Get-AzCosmosDBSqlRoleDefinition'

PS:\>Get-HELP Get-AzCosmosDBSqlRoleDefinition -Full

NAME

Get-AzCosmosDBSqlRoleDefinition

SYNOPSIS

Gets the CosmosDB Role Definition.

SYNTAX

```
Get-AzCosmosDBSqlRoleDefinition -AccountName <System.String> [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Id <System.String>]  
-ResourceGroupName <System.String>  
[<CommonParameters>]
```

Get-AzCosmosDBSqlRoleDefinition [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Id <System.String>
-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>
[<CommonParameters>]

DESCRIPTION

The Get-AzCosmosDBSqlRoleDefinition cmdlet gets the list of all existing CosmosDB Sql Role Definitions for a given ResourceGroupName, AccountName and gets a single

CosmosDB Sql Database for a given ResourceGroupName, AccountName, and Id. Id can be either fully qualified or just the Guid.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Id <System.String>

Role Definition Id.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSSqlRoleDefinitionGetResults

NOTES

----- Example 1 -----

```
Get-AzCosmosDBSqlRoleDefinition -AccountName accountName -ResourceGroupName resourceGroupName -Id id
```

RoleName : roleName

Id

:

/subscriptions/subId/resourceGroups/resourceGroupName/providers/Microsoft.DocumentDB/databaseAccounts/accountName/sqlRoleDefinitions/id

Type : CustomRole

Permissions : {Microsoft.Azure.Management.CosmosDB.Models.Permission}

AssignableScopes

:

{/subscriptions/subId/resourceGroups/resourceGroupName/providers/Microsoft.DocumentDB/databaseAccounts/accountName}

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/get-azcosmosdbsqlroledefinition>