



Windows PowerShell Get-Help on Cmdlet 'Get-AzCosmosDBTable'

PS:\>Get-HELP Get-AzCosmosDBTable -Full

NAME

Get-AzCosmosDBTable

SYNOPSIS

Gets a CosmosDB Table.

SYNTAX

```

Get-AzCosmosDBTable -AccountName <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>] -ResourceGroupName <System.String> [<CommonParameters>]

Get-AzCosmosDBTable [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>] -ParentObject
<Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults> [<CommonParameters>]

```

DESCRIPTION

The Get-AzCosmosDBTable cmdlet gets an existing Table.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Name of the Table.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSDatabaseAccountGetResults>

CosmosDB Account object

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-ResourceGroupName <System.String>
Name of resource group.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSTableGetResults

Microsoft.Azure.Commands.CosmosDB.Models.PSThroughputSettingsGetResults

NOTES

----- Example 1 -----

```
Get-AzCosmosDBTable -AccountName "account" -Name "tableName" -ResourceGroupName "rgName"
```

Name	Id	Resource
------	----	----------

{name}	{id}	Microsoft.Azure.Commands.CosmosDB.Models.PSTableGetPropertiesResource
--------	------	---

Resource object contains rid, _ts, etag properties of the Table.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/get-azcosmosdbtable>