



## ***Windows PowerShell Get-Help on Cmdlet 'Get-AzDataBoxEdgeJob'***

***PS:\>Get-HELP Get-AzDataBoxEdgeJob -Full***

### NAME

Get-AzDataBoxEdgeJob

### SYNOPSIS

Gets the jobs scheduled on a device.

### SYNTAX

```
Get-AzDataBoxEdgeJob [-ResourceGroupName] <System.String> [-DeviceName] <System.String> [-Name]
<System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzDataBoxEdgeJob [-Name] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -DeviceObject
    <Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice> [<CommonParameters>]
```

```
Get-AzDataBoxEdgeJob [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ResourceId
    <System.String>
```

## DESCRIPTION

The Get-AzDataBoxEdgeJob cmdlet gets the active jobs on a Data Box Edge device. You can mention the Name parameter to get details of a specific job.

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DeviceName <System.String>

Name of the device

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DeviceObject <Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice>

Please provide corresponding device object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Name of the Job, Generally a GUID

Required? true

Position? 2

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Azure ResourceId

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see  
about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice

## OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeJob

## NOTES

----- Example 1 -----

```
Get-AzDataBoxEdgeJob -ResourceGroupName resourceGroupName -DeviceName deviceName -Name  
1f2d8f1b-9104-49c3-b780-76db9abe7bd1
```

| Name                                 | Device-Name | status    |
|--------------------------------------|-------------|-----------|
| 1f2d8f1b-9104-49c3-b780-76db9abe7bd1 | deviceName  | Scheduled |

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.databoxedge/get-azdataboxedgejob>

