



### ***Windows PowerShell Get-Help on Cmdlet 'Get-AzDataBoxEdgeOrder'***

***PS:\>Get-HELP Get-AzDataBoxEdgeOrder -Full***

#### **NAME**

Get-AzDataBoxEdgeOrder

#### **SYNOPSIS**

Get the order details for a device

#### **SYNTAX**

```
Get-AzDataBoxEdgeOrder [-ResourceGroupName] <System.String> [-DeviceName] <System.String> [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]  
[<CommonParameters>]
```

Get-AzDataBoxEdgeOrder [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -DeviceObject  
<Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice> [<CommonParameters>]

```
Get-AzDataBoxEdgeOrder [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ResourceId  
<System.String>  
[<CommonParameters>]
```

## DESCRIPTION

The Get-AzDataBoxEdgeOrder cmdlet gets the order details for a Data Box Edge device.

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DeviceName <System.String>

Resource Group Name

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DeviceObject <Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice>

Please provide corresponding device object

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <System.String>

Azure ResourceId

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice

System.String

## OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeOrder

## NOTES

----- Example 1 -----

Get-AzDataBoxEdgeOrder -ResourceGroupName resourceGroupName -DeviceName deviceName

| DeviceName | ResourceGroupName | Status | UpdatedDatetime |
|------------|-------------------|--------|-----------------|
|------------|-------------------|--------|-----------------|

|       |       |       |       |
|-------|-------|-------|-------|
| ----- | ----- | ----- | ----- |
|-------|-------|-------|-------|

|            |                   |           |                       |
|------------|-------------------|-----------|-----------------------|
| deviceName | resourceGroupName | Untracked | 01-Jan-01 12:00:00 AM |
|------------|-------------------|-----------|-----------------------|

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.databoxedge/get-azdataboxedgeorder>